



**Program Directory for
IBM WebSphere Developer for zSeries
Common Access Repository Manager**

V6.0.1

Program Number 5724-L44

FMID HCMA601

for Use with
z/OS Version 1 Release 4 or later

Document Date: November, 2005

GI10-3367-00

Note!

Before using this information and the product it supports, be sure to read the general information under 7.0, "Notices" on page 22.

A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© **Copyright International Business Machines Corporation 2005. All rights reserved.**

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Contents

1.0 Introduction	1
1.1 WD/Z CARMA Description	1
1.2 WD/Z CARMA FMIDs	2
2.0 Program Materials	3
2.1 Basic Machine-Readable Material	3
2.2 Optional Machine-Readable Material	3
2.3 Program Publications	3
2.3.1 Basic Program Publications	3
2.3.2 Optional Program Publications	4
2.4 Program Source Materials	4
2.5 Publications Useful During Installation	4
3.0 Program Support	5
3.1 Program Services	5
3.2 Preventive Service Planning	5
3.3 Statement of Support Procedures	5
4.0 Program and Service Level Information	6
4.1 Program Level Information	6
4.2 Service Level Information	6
5.0 Installation Requirements and Considerations	7
5.1 Driving System Requirements	7
5.1.1 Machine Requirements	7
5.1.2 Programming Requirements	7
5.2 Target System Requirements	8
5.2.1 Machine Requirements	8
5.2.2 Programming Requirements	8
5.2.2.1 Installation Requisites	8
5.2.2.2 Operational Requisites	8
5.2.2.3 Toleration/Coexistence Requisites	9
5.2.2.4 Incompatibility (Negative) Requisites	9
5.2.3 DASD Storage Requirements	9
5.3 FMIDs Deleted	12
5.4 Special Considerations	12
6.0 Installation Instructions	13
6.1 Installing WD/Z CARMA	13
6.1.1 SMP/E Considerations for Installing WD/Z CARMA	13
6.1.2 SMP/E Options Subentry Values	13
6.1.3 Overview of the installation steps	14

6.1.4	Upload the Sample JCL from the CD-ROM	14
6.1.5	Expand the sample jcl file by using the TSO receive command:	15
6.1.6	Sample Jobs	16
6.1.7	Run the job to allocate sequential data sets to FTP into	16
6.1.8	Upload the Compressed RELFILES and SMPMCS from the CD-ROM	16
6.1.9	Expand the RELFILES	17
6.1.10	(optional) Allocate and initialize the SMP/E data sets.	18
6.1.11	Perform SMP/E RECEIVE	18
6.1.12	Allocate SMP/E Target and Distribution Libraries	18
6.1.13	Create DDDEF Entries	18
6.1.14	Perform SMP/E APPLY	19
6.1.15	Perform SMP/E ACCEPT	20
6.1.16	Run REPORT CROSSZONE	21
6.2	Activating WD/Z CARMA	21
7.0	Notices	22
7.1	Trademarks	23
Reader's Comments		24

Figures

1.	Basic Material: Other Unlicensed or Licensed Publications	3
2.	Publications Useful During Installation	4
3.	PSP Upgrade and Subset ID	5
4.	Component IDs	5
5.	Driving System Software Requirements	7
6.	Mandatory Installation Requisites	8
7.	Mandatory Operational Requisites	9
8.	Total DASD Space Required by WD/Z CARMA	9
9.	Storage Requirements for WD/Z CARMA Target Libraries	11
10.	Storage Requirements for WD/Z CARMA Distribution Libraries	11
11.	SMP/E Options Subentry Values	13
12.	User Entered Values	15
13.	Sample Installation Jobs	16

1.0 Introduction

This Program Directory is intended for the system programmer responsible for program installation and maintenance. It contains information concerning the material and procedures associated with the installation of IBM WebSphere Developer for zSeries CARMA. This publication refers to IBM WebSphere Developer for zSeries CARMA as WD/Z CARMA.

The Program Directory contains the following sections:

- 2.0, “Program Materials” on page 3 identifies the basic and optional program materials and documentation for WD/Z CARMA.
- 3.0, “Program Support” on page 5 describes the IBM support available for WD/Z CARMA.
- 4.0, “Program and Service Level Information” on page 6 lists the APARs (program level) and PTFs (service level) incorporated into WD/Z CARMA.
- 5.0, “Installation Requirements and Considerations” on page 7 identifies the resources and considerations required for installing and using WD/Z CARMA.
- 6.0, “Installation Instructions” on page 13 provides detailed installation instructions for WD/Z CARMA. It also describes the procedures for activating the functions of WD/Z CARMA, or refers to appropriate publications.

Before installing WD/Z CARMA, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that were supplied with this program in softcopy form as well as this Program Directory and then keep them for future reference. Section 3.2, “Preventive Service Planning” on page 5 tells you how to find any updates to the information and procedures in this Program Directory.

WD/Z CARMA is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The Program Directory is provided in softcopy form on the CBPDO tape which is identical to the hardcopy form provided with your order. Your CBPDO contains a softcopy preventive service planning (PSP) upgrade for this product. All service and HOLDDATA for WD/Z CARMA are included on the CBPDO tape.

Do not use this Program Directory if you are installing WD/Z CARMA with a SystemPac or ServerPac. When using these offerings, use the jobs and documentation supplied with the offering. This documentation may point you to specific sections of the Program Directory as required.

1.1 WD/Z CARMA Description

Common Access Repository Manager (CARMA) provides a unified interface and set of services for accessing 390-based source code management (SCM) tools, as well as a generic GUI client that you can use as a framework for creation of custom SCM GUIs. The Developer's Guide gives the detailed instructions for a customer whom would like to do one of the following tasks: to write a custom Repository Access Module (RAM) for any SCM which we do not support out-of-the-box; to access CARMA functions from their own host application (instead of through the WD/z UI); or, to extend the Eclipse UI to access

any SCM which we do not support out-of-the-box. The intended audience of this document will vary depending on which task the customer is trying to accomplish. Someone implementing a custom RAM would be a host developer whom has some knowledge of their SCM's ISPF command line interface. A host programmer may want to access CARMA functions from his/her own host application. An Eclipse programmer would customize the Eclipse UI for their own SCM.

1.2 WD/Z CARMA FMIDs

WD/Z CARMA consists of the following FMIDs:

HCMA601

2.0 Program Materials

An IBM program is identified by a program number. The program number for WD/Z CARMA is 5724-L44.

Basic Machine-Readable Materials are materials that are supplied under the base license and feature numbers, and are required for the use of the product. Optional Machine-Readable Materials are orderable under separate feature numbers, and are not required for the product to function.

The program announcement material describes the features supported by WD/Z CARMA. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is magnetic tape or downloadable files. It is installed using SMP/E, and is in SMP/E RELFILE format. See 6.0, "Installation Instructions" on page 13 for more information about how to install the program.

Information about the physical tape for the Basic Machine-Readable Materials for WD/Z CARMA can be found in the *CBPDO Memo To Users Extension*.

2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for WD/Z CARMA.

2.3 Program Publications

The following sections identify the basic and optional publications for WD/Z CARMA.

2.3.1 Basic Program Publications

Figure 1 identifies the basic unlicensed or licensed publications that are not available in hardcopy form, but are available through the internet or other media for WD/Z CARMA.

Publication Title	Form Number	How Available
WebSphere Developer for zSeries - Common Access Repository Manager Developer's Guide	SC31-6914-00	On Product CD

2.3.2 Optional Program Publications

No optional publications are provided for WD/Z CARMA.

2.4 Program Source Materials

No program source materials or viewable program listings are provided for WD/Z CARMA.

2.5 Publications Useful During Installation

The publications listed in Figure 2 may be useful during the installation of WD/Z CARMA. To order copies, contact your IBM representative or visit the IBM Publications Center on the World Wide Web at: <http://www.ibm.com/shop/publications/order>

<i>Figure 2. Publications Useful During Installation</i>	
Publication Title	Form Number
<i>IBM SMP/E for z/OS and OS/390 User's Guide</i>	SA22-7773
<i>IBM SMP/E for z/OS and OS/390 Commands</i>	SA22-7771
<i>IBM SMP/E for z/OS and OS/390 Reference</i>	SA22-7772
<i>IBM SMP/E for z/OS and OS/390 Messages, Codes, and Diagnosis</i>	GA22-7770

3.0 Program Support

This section describes the IBM support available for WD/Z CARMA.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

Before installing WD/Z CARMA, you should review the current Preventive Service Planning (PSP) information. If you obtained WD/Z CARMA as part of a CBPDO, there is HOLDDATA and PSP information included on the CBPDO.

If the CBPDO for WD/Z CARMA is more than two weeks old when you install it, you should contact the IBM Support Center, use S/390 SoftwareXcel to obtain the current "PSP Bucket" or obtain the current PSP from the web at <https://techsupport.services.ibm.com/server/390.psp390>

For program support, access the Software Support web site at <http://www-3.ibm.com/software/support/>

PSP Buckets are identified by UPGRADEs, which specify product levels, and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for WD/Z CARMA are:

<i>Figure 3. PSP Upgrade and Subset ID</i>		
UPGRADE	SUBSET	Description
5724L44	H001600	WD4Z CARMA

3.3 Statement of Support Procedures

Report any difficulties you have using this program to your IBM Support Center. If an APAR is required, the Support Center will provide the address to which any needed documentation can be sent.

Figure 4 identifies the component IDs (COMPID) for WD/Z CARMA.

<i>Figure 4. Component IDs</i>			
FMID	COMPID	Component Name	RETAIN Release
HCMA601	5724L4430	WD/z CARMA	601

4.0 Program and Service Level Information

This section identifies the program and any relevant service levels of WD/Z CARMA. The program level refers to the APAR fixes incorporated into the program. The service level refers to the PTFs incorporated into the program.

4.1 Program Level Information

No APARs have been incorporated into WD/Z CARMA.

4.2 Service Level Information

No PTFs against this release of WD/Z CARMA have been incorporated into the product tape.

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating WD/Z CARMA. The following terminology is used:

- *Driving system*: the system used to install the program.
- *Target system*: the system on which the program is installed.

In many cases, the same system can be used as both a driving system and a target system. However, you may want to set up a clone of your system to use as a target system by making a separate IPL-able copy of the running system. The clone should include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Some cases where two systems should be used include the following:

- When installing a new level of a product that is already installed, the new product will delete the old one. By installing onto a separate target system, you can test the new product while still keeping the old one in production.
- When installing a product that shares libraries or load modules with other products, the installation can disrupt the other products. Installing onto a test system or clone will allow you to assess these impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install WD/Z CARMA.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

<i>Figure 5. Driving System Software Requirements</i>	
Program Number	Product Name and Minimum VRM/Service Level
Any one of the following:	
5694-A01	z/OS V1.04.0 or later
5655-G44	IBM SMP/E for z/OS and OS/390 V3.02.0 or later

5.2 Target System Requirements

This section describes the environment of the target system required to install and use WD/Z CARMA.

WD/Z CARMA installs in the z/OS (Z038) SREL.

5.2.1 Machine Requirements

The target system can run in any hardware environment that supports the required software.

5.2.2 Programming Requirements

5.2.2.1 Installation Requisites

An installation requisite is defined as a product that is required and **must** be present or one that is not required but **should** be present on the system for the successful installation of this product.

A mandatory installation requisite identifies products that are required, without exception, or this product **will not install** on your system. This includes products specified as PREs or REQs.

Figure 6. Mandatory Installation Requisites

Program Number	Product Name and Minimum VRM/Service Level
5694-A01	z/OS V1.04.0 or later

A conditional installation requisite identifies products that are **not** required for successful install but may resolve such things as certain warning messages at installation time. They include products that are specified as IF REQs.

WD/Z CARMA has no conditional installation requisites.

5.2.2.2 Operational Requisites

An operational requisite is defined as a product that is required and **must** be present or a product that is not required but **should** be present on the system in order for this product to operate all or some of its functions.

A mandatory operational requisite identifies products that are required, without exception, or this product **will not operate** its basic function unless the requisite is met. This includes products specified as PREs or REQs.

<i>Figure 7. Mandatory Operational Requisites</i>	
Program Number	Product Name and Minimum VRM/Service Level
5724-L44	IBM WebSphere Developer for zSeries RSE + ICU, V6.0.1 or later

A conditional operational requisite identifies products that are **not required** for the basic function but are needed at run time for this product to utilize specific functions. They may include products specified as IF REQs.

WD/Z CARMA has no conditional operational requisites.

5.2.2.3 Toleration/Coexistence Requisites

A toleration/coexistence requisite is defined as a product which must be present on a sharing system. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD at different time intervals.

WD/Z CARMA has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites

A negative requisite identifies products which must *not* be installed on the same system as this product.

WD/Z CARMA has no negative requisites.

5.2.3 DASD Storage Requirements

WD/Z CARMA libraries can reside on all supported DASD types.

Figure 8 lists the total space required for each type of library.

<i>Figure 8. Total DASD Space Required by WD/Z CARMA</i>	
Library Type	Total Space Required
Target	40 3390 Tracks
Distribution	40 3390 Tracks

Notes:

1. IBM recommends use of system determined block sizes for efficient DASD utilization for all non-RECFM U data sets. For RECFM U data sets, IBM recommends a block size of 32760, which is the most efficient from a performance and DASD utilization perspective.

2. Abbreviations used for the data set type are:

- U** Unique data set, allocated by this product and used only by this product. To determine the correct storage needed for this data set, this table provides all required information; no other tables (or Program Directories) need to be referenced for the data set size.
- S** Shared data set, allocated by this product and used by this product and others. To determine the correct storage needed for this data set, the storage size given in this table needs to be added to other tables (perhaps in other Program Directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
- E** Existing shared data set, used by this product and others. This data set is NOT allocated by this product. To determine the correct storage needed for this data set, the storage size given in this table needs to be added to other tables (perhaps in other program directories). This existing data set must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old one and reclaim the space used by the old release and any service that had been installed. You can determine whether or not these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information on the names and sizes of the required data sets, please refer to 6.1.12, "Allocate SMP/E Target and Distribution Libraries" on page 18.

3. Abbreviations used for the HFS Path type are:

- N** New path, created by this product.
- X** Path created by this product, but may already exist from a previous release.
- P** Previously existing path, created by another product.

4. All target and distribution libraries listed have the following attributes:

- The default name of the data set may be changed.
- The default block size of the data set may be changed.
- The data set may be merged with another data set that has equivalent characteristics.
- The data set may be either a PDS or a PDSE.

5. All target libraries listed have the following attributes:

- The data set may be SMS-managed.
- It is not required for the data set to be SMS-managed.
- It is not required for the data set to reside on the IPL volume.
- The values in the "Member Type" column are not necessarily the actual SMP/E element types identified in the SMPMCS.

6. All target libraries listed which contain load modules have the following attributes:

- The data set may be in the LPA.
- It is not required for the data set to be in the LPA.
- The data set may be in the LNKLIST.
- It is not required for the data set to be APF-authorized.

The following figures describe the target and distribution libraries required to install WD/Z CARMA. The storage requirements of WD/Z CARMA must be added to the storage required by other programs having data in the same library.

Note: The data in these tables should be used when determining which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

Figure 9. Storage Requirements for WD/Z CARMA Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SCRACLST	CLIST	ANY	U	PDS	FB	80	1	1
SCRAJCL	INSTALL JCL	ANY	U	PDS	FB	80	2	2
SCRALOAD	LMOD	ANY	U	PDS	U	0	8	10
SCRASAM	SAMPLES	ANY	U	PDS	FB	80	20	5
SCRAVSAM	VSAM	ANY	U	PDS	FB	180	3	2
SCRAVSAY	VSAM	ANY	U	PDS	FB	2150	7	2

Figure 10. Storage Requirements for WD/Z CARMA Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ACRACLST	U	PDS	FB	80	1	1
ACRAJCL	U	PDS	FB	80	2	2
ACRALOAD	U	PDS	U	0	8	10
ACRASAM	U	PDS	FB	80	20	5
ACRAVSAM	U	PDS	FB	180	3	2
ACRAVSAY	U	PDS	FB	2150	7	2

5.3 FMIDs Deleted

Installing WD/Z CARMA may result in the deletion of other FMIDs. To see what FMIDs will be deleted, examine the ++VER statement in the product's SMPMCS.

If you do not wish to delete these FMIDs at this time, you must install WD/Z CARMA into separate SMP/E target and distribution zones.

Note: These FMIDs will not automatically be deleted from the Global Zone. Consult the SMP/E manuals for instructions on how to do this.

5.4 Special Considerations

WD/Z CARMA has no special considerations for the target system.

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of WD/Z CARMA.

Please note the following:

- If you want to install WD/Z CARMA into its own SMP/E environment, use sample job CRASMPE or consult the SMP/E manuals for instructions on creating and initializing the SMPCSI and the SMP/E control data sets.
- Sample jobs have been provided to help perform some or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries required for SMP/E execution have been defined in the appropriate zones.
- The SMP/E dialogs may be used instead of the sample jobs to accomplish the SMP/E installation steps.

6.1 Installing WD/Z CARMA

6.1.1 SMP/E Considerations for Installing WD/Z CARMA

This release of WD/Z CARMA is installed using the SMP/E RECEIVE, APPLY, and ACCEPT commands. The SMP/E dialogs may be used to accomplish the SMP/E installation steps.

6.1.2 SMP/E Options Subentry Values

The recommended values for some SMP/E CSI subentries are shown in Figure 11. Use of values lower than these may result in failures in the installation process. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. Refer to the SMP/E manuals for instructions on updating the global zone.

SUB-ENTRY	Value	Comment
DSSPACE	(600,200,100)	Space allocation for temporary data sets
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.

6.1.3 Overview of the installation steps

Overview of steps required to install IBM WebSphere Developer for zSeries CARMA.

1. Upload sample JCL from the CD-ROM
2. Expand the sample JCL
3. Sample JCL
4. Allocate sequential data sets
5. Upload the RELFILES and SMPMCS from the CD-ROM
6. Expand the RELFILES
7. (optional) Allocate and initialize the SMP/E data sets.
8. Perform SMP/E RECEIVE
9. Allocate target and distribution libraries
10. Create DDDEF entries
11. Perform SMP/E APPLY
12. Perform SMP/E ACCEPT

6.1.4 Upload the Sample JCL from the CD-ROM

On the CD-ROM, there is a file containing sample installation JCL. This sample JCL contains a member that will allocate the sequential data sets on z/OS for the RELFILES and SMPMCS contained on the CD-ROM and other members to perform the SMP/E processing. Perform the following steps to upload it from the CD-ROM to z/OS:

1. Allocate a data set on z/OS to be the target of the upload. You can do this by submitting the job below or by creating a data set with these characteristics. Add a job card and modify the parameters to meet your site's requirements before submitting. **hlq** will be the high level qualifier you choose to use for this data set.

```
//ALLOC1 EXEC PGM=IEFBR14
//*
//FTPALLO DD DSN=hlq.IBM.HCMA601.SAMPLE.JCL.BIN,
// DISP=(NEW,CATLG,DELETE),
// DSORG=PS,
// RECFM=FB,
// LRECL=80,
// BLKSIZE=6160,
// SPACE=(TRK,(2,1)),
// UNIT=SYSALLDA
//* VOL=SER=&TVOL1
```

2. Upload the sample jcl file in binary format from the CD-ROM to z/OS data set. If the CD-ROM is attached to a Windows NT system, you can use FTP from a command prompt to upload the file. In the

sample dialog shown below, commands or other information entered by the user are in bold, and the following values are assumed:

<i>Figure 12. User Entered Values</i>	
User enters:	Values
mvsaddr	TCP/IP address or hostname of the z/OS system
tsouid	Your TSO user ID
tsopw	Your TSO password
d:	Your CD-ROM drive
hlq	High-level qualifier you used for the data set you allocated in the job above

```
C:\>ftp mvsaddr
Connected to mvsaddr.
220-FTPD1 IBM FTP CS V1R2 at mvsaddr, 07:18:16 on 2005-04-15.
220 Connection will close if idle for more than 60 minutes.
```

```
User (mvsaddr:(none)): tsouid
```

```
331 Send password please.
Password: tsopw
230 tsouid is logged on. Working directory is "tsouid".
```

```
ftp> cd ..
250 " "is the working directory name prefix.
```

```
ftp> cd hlq
250 "hlq." is the working directory name prefix.
```

```
ftp> binary
200 Representation type is Image
```

```
ftp> put d:\HCMA601\ibm.hcma601.sample.jcl.bin
200 Port request OK.
125 Storing data set hlq.HCMA601.SAMPLE.JCL.BIN
250 Transfer completed successfully.
73360 bytes sent in 0.21 seconds
```

```
ftp> quit
221 Quit command received. Goodbye.
```

6.1.5 Expand the sample jcl file by using the TSO receive command:

```
receive inda('hlq.ibm.HCMA601.sample.jcl.bin')
```

This will create a data set named **hlq.HCMA601.SAMPLE.JCL**.

6.1.6 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install WD/Z CARMA:

Figure 13. Sample Installation Jobs

Job Name	Job Type	Description	RELFILE
CRAACCEP	ACCEPT	Sample ACCEPT job	IBM.HCMA601.F1
CRAALLOC	ALLOCATE	Sample job to allocate target and distribution libraries	IBM.HCMA601.F1
CRAAPPLY	APPLY	Sample APPLY job	IBM.HCMA601.F1
CRADDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.HCMA601.F1
CRARECEV	RECEIVE	Sample RECEIVE job	IBM.HCMA601.F1
CRASEQAL	Alloc SEQ DSNs	Sample job to allocate sequential data sets to be used during the upload process	IBM.HCMA601.F1
CRASMPE	SMPE setup	Sample job to create SMP/E CSI and work data sets (optional)	IBM.HCMA601.F1

You can access the sample installation jobs by performing an SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 13 to find the appropriate relfile data set.

6.1.7 Run the job to allocate sequential data sets to FTP into

Edit and submit sample job **CRASEQAL** in the **hlq.HCMA601.SAMPLE.JCL** data set to allocate data sets on z/OS to be used during the upload process. Use the instructions in the sample job for information on changes required.

Expected Return Codes and Messages: RC=0

6.1.8 Upload the Compressed RELFILES and SMPMCS from the CD-ROM

1. Upload the files in binary format from the CD-ROM to the z/OS data set. If the CD-ROM is attached to a Windows NT system, you can use FTP from a command prompt to upload the files:

```
C:\>ftp mvsaddr
Connected to mvsaddr.
220-FTPD1 IBM FTP CS V1R2 at mvsaddr, 07:18:16 on 2005-04-15.
220 Connection will close if idle for more than 60 minutes.
```

```
User (mvsaddr:(none)): tsuid
```

```

331 Send password please.
Password: tsopw
230 tsouid is logged on. Working directory is "tsouid.".

ftp> cd ..
250 " " is the working directory name prefix.

ftp> cd h1q
250 "h1q." is the working directory name prefix.

ftp> binary
200 Representation type is Image

ftp> prompt
Interactive mode Off.

ftp> mput d:\HCMA601\ibm.HCMA601.f*
200 Port request OK.
125 Storing data set h1q.IBM.HCMA601.F1.BIN
250 Transfer completed successfully.
1055440 bytes sent in 0.15 seconds
200 Port request OK.
125 Storing data set h1q.IBM.HCMA601.F2.BIN
250 Transfer completed successfully.
297280 bytes sent in 0.15 seconds
200 Port request OK.
125 Storing data set h1q.IBM.HCMA601.F3.BIN
250 Transfer completed successfully.
136480 bytes sent in 0.26 seconds 200 Port request OK.
125 Storing data set h1q.IBM.HCMA601.F4.BIN
250 Transfer completed successfully.
326400 bytes sent in 0.26 seconds

ftp> put d:\HCMA601\ibm.HCMA601.smpmcs
200 Port request OK.
125 Storing data set h1q.IBM.HCMA601.SMPMCS
250 Transfer completed successfully.
6720 bytes sent in 0.01 seconds

ftp> quit
221 Quit command received. Goodbye.

```

6.1.9 Expand the RELFILES

You can expand the RELFILES by using the TSO receive command:

```
receive inda('h1q.ibm.HCMA601.f1.bin')
receive inda('h1q.ibm.HCMA601.f2.bin')
receive inda('h1q.ibm.HCMA601.f3.bin')
receive inda('h1q.ibm.HCMA601.f4.bin')
```

When prompted on the TSO receive commands, use the appropriate DSNAME from the list below:

```
DS('h1q.IBM.HCMA601.F1')
DS('h1q.IBM.HCMA601.F2')
DS('h1q.IBM.HCMA601.F3')
DS('h1q.IBM.HCMA601.F4')
```

6.1.10 (optional) Allocate and initialize the SMP/E data sets.

A Sample job, CRASMPE, to allocate and prime an SMP/E CSI and work data sets is provided if you choose to install WD/Z CARMA in it's own CSI.

1. CRASMPE

Expected Return Codes and Messages: RC=0

6.1.11 Perform SMP/E RECEIVE

Having obtained WD/Z CARMA as part of a CBPDO, use the RCVPDO job found in the CBPDO RIMLIB data set to RECEIVE the WD/Z CARMA FMIDs as well as any service, HOLDDATA, or preventive service planning (PSP) information included on the CBPDO tape. For more information, refer to the documentation included with the CBPDO.

Expected Return Codes and Messages: RC=0

6.1.12 Allocate SMP/E Target and Distribution Libraries

Edit and submit sample job CRAALLOC to allocate the SMP/E target and distribution libraries for WD/Z CARMA. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: RC=0

6.1.13 Create DDDEF Entries

Edit and submit sample job CRADDDEF to create DDDEF entries for the SMP/E target and distribution libraries for WD/Z CARMA. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: RC=0

6.1.14 Perform SMP/E APPLY

Edit and submit sample job CRAAPPLY to perform an SMP/E APPLY CHECK for WD/Z CARMA. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the following on the APPLY CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of **ERRORS** and not of **WARNINGS** (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

Enhanced HOLDDATA introduced ERROR HOLDS against FMIDs for HIPER APARs. Prior to installing, you should ensure you have the latest Enhanced HOLDDATA (available at url <http://service.software.ibm.com/holdata/390holddata.html>). The FMID(s) should be installed regardless of the status of unresolved HIPERs, however, the software should not be deployed until the unresolved HIPERs have been analyzed to determine applicability.

There are two methods to complete an FMID installation where ++HOLDS for HIPERs exist for the FMID(s) being installed:

1. To ensure that all critical service is installed with the FMID(s), add the SOURCEIDs of PRP, and HIPER to the APPLY command. There may be PE or HIPER APARs that do not have resolving PTFs available yet. You need to analyze the symptom flags to determine if you want to BYPASS the specific ERROR HOLDS and continue the FMID installation.

```
APPLY S(fmid,fmid,...)
FORFMID(fmid,fmid,...)
SOURCEID(PRP,HIPER,...)
GROUPEXTEND .
```

This method requires more initial research, but will provide resolution for all HIPERs that have fixes available and are not in a PE chain. There may still be unresolved PEs or HIPERs which will require the use of BYPASS.

2. To install the FMID(s) as it would have been installed prior to Enhanced HOLDDATA, you can add a BYPASS(HOLDCLASS(HIPER)) operand to the APPLY command. This will allow the FMID to be installed even though there are HIPER ERROR HOLDS against it. Note that not all ERROR HOLDS were bypassed, only the HIPER ERROR HOLDS. After the FMID(s) are installed, the SMP/E REPORT ERRSYSMODS command should be run to identify any missing HIPER maintenance.

```
APPLY S(fmid,fmid,...)
BYPASS(HOLDCLASS(HIPER))
other parameters documented in the program directory...
```

This method is the quicker of the two, but requires subsequent review of the REPORT ERRSYSMODS to investigate any HIPERs.

If you bypass any HOLDS during the installation of the FMID(s) because fixing PTFs were not yet available you can use the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink to be notified when the fixing PTF is available.

Once you have taken any actions indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Note: The GROUPEXTEND operand indicates that SMP/E apply all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from APPLY CHECK: RC=0

Expected Return Codes and Messages from APPLY: RC=0

6.1.15 Perform SMP/E ACCEPT

Edit and submit sample job CRAACCEP to perform an SMP/E ACCEPT CHECK for WD/Z CARMA. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the following on the ACCEPT CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of **ERRORS** and not of **WARNINGS** (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

Before using SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. This will cause entries produced from JCLIN to be saved in the distribution zone whenever a SYSMOD containing inline JCLIN is ACCEPTed. For more information on the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E manuals.

Once you have taken any actions indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accept all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from ACCEPT CHECK: RC=0

If PTFs containing replacement modules are being ACCEPTed, SMP/E ACCEPT processing will linkedit/bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder may issue messages documenting unresolved external references, resulting in a return code of 4 from the ACCEPT step. These messages can be ignored, because the distribution libraries are not executable and the unresolved external references will not affect the executable system libraries.

Expected Return Codes and Messages from ACCEPT: RC=0

6.1.16 Run REPORT CROSSZONE

The SMP/E REPORT CROSSZONE command will identify requisites defined for products that have been installed in separate zones. This command will also create APPLY and ACCEPT commands in the SMPPUNCH data set which you can use to install those cross-zone requisites it identifies.

After you have installed WD/Z CARMA, it is recommended that you run REPORT CROSSZONE against the new or updated target and distribution zones. REPORT CROSSZONE requires a global zone with ZONEINDEX entries describing all the target and distribution libraries to be reported on.

For more information on REPORT CROSSZONE, see the SMP/E manuals.

6.2 Activating WD/Z CARMA

The publication *IBM WebSphere Developer for zSeries Host Configuration Guide - SC31-6930-00* contains the step-by-step procedures to activate the functions of WD/Z CARMA.

7.0 Notices

References in this document to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe on any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, is the user's responsibility.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, New York 10504-1785
USA

For online versions of this book, we authorize you to:

- Copy, modify, and print the documentation contained on the media, for use within your enterprise, provided you reproduce the copyright notice, all warning statements, and other required statements on each copy or partial copy.
- Transfer the original unaltered copy of the documentation when you transfer the related IBM product (which may be either machines you own, or programs, if the program's license terms permit a transfer). You must, at the same time, destroy all other copies of the documentation.

You are responsible for payment of any taxes, including personal property taxes, resulting from this authorization.

THERE ARE NO WARRANTIES, EXPRESS OR IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Some jurisdictions do not allow the exclusion of implied warranties, so the above exclusion may not apply to you.

Your failure to comply with the terms above terminates this authorization. Upon termination, you must destroy your machine readable documentation.

7.1 Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

CBPDO

IBM®

SystemPac

ServerPac

ResourceLink

ServiceLink

WebSphere

z/OS

Reader's Comments

Program Directory for IBM WebSphere Developer for zSeries CARMA, November, 2005

You may use this form to comment about this document, its organization, or subject matter with the understanding that IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.

For each of the topics below please indicate your satisfaction level by circling your choice from the rating scale. If a statement does not apply, please circle N.

RATING SCALE						
very satisfied	<----->				very dissatisfied	not applicable
1	2	3	4	5	N	

	Satisfaction					
Ease of product installation	1	2	3	4	5	N
Contents of Program Directory	1	2	3	4	5	N
Installation Verification Programs	1	2	3	4	5	N
Time to install the product	1	2	3	4	5	N
Readability and organization of Program Directory tasks	1	2	3	4	5	N
Necessity of all installation tasks	1	2	3	4	5	N
Accuracy of the definition of the installation tasks	1	2	3	4	5	N
Technical level of the installation tasks	1	2	3	4	5	N
Ease of getting the system into production after installation	1	2	3	4	5	N

How did you order this product?

- CBPDO
- CustomPac
- ServerPac
- Independent
- Other

Is this the first time your organization has installed this product?

- Yes
- No

Were the people who did the installation experienced with the installation of z/OS products?

- Yes

Janice Rogers
IBM Corporation
Building 500/F208
4205 S. Miami Blvd.
Durham, North Carolina 27703

FAX Number: (919) 254-0206

E-Mail: janicer@us.ibm.com

.



Printed in U.S.A.

G110-3367-00

